


Sample Information

Sample Type : Essential Oil
 Sample Name : Lavandula latifolia
 Injection Volume : 0.10

Lavender Spike
 Lot# SPN26-NT
 Country: Spain



Chromatogram Lavandula latifolia



R.Time	Name	Area%
13.014	alpha-Pinene	0.15
13.953	Camphene	0.16
15.252	Sabinene	0.01
15.571	beta-Pinene	0.02
15.910	3-Octanone	0.65
16.195	Myrcene	0.57
17.145	Pseudolimonene	0.08
17.447	delta-3-Carene	0.15
17.574	Hexyl acetate	0.45
17.970	alpha-Terpinene	0.01
18.445	para-Cymene	0.02
18.768	Limonene	2.19
19.004	1,8-cineole	27.45
19.151	cis-beta-Ocimene	1.09
19.855	trans-beta-Ocimene	2.53
21.487	cis-Linalool oxide (furanoid)	0.06
22.578	trans-Linalool oxide (furanoid)	0.11
23.588	Linalool	44.05
23.732	Hotrienol	0.03
25.421	allo-Ocimene	0.10
26.264	neo-allo-Ocimene	0.01
26.819	Camphor	12.09
27.908	Isoborneol	0.02
28.509	Borneol	0.56
29.104	Terpinen-4-ol	1.69
30.099	alpha-Terpineol	1.20
31.140	Octyl acetate	0.22
32.078	Nerol	0.05
33.831	Linalyl acetate	1.29
36.223	Bornyl acetate	0.32
41.111	Neryl acetate	0.24
42.396	Geranyl acetate	0.42
45.136	beta-Caryophyllene	1.56
52.551	trans-alpha-Bisabolene	0.45
		100.00